


# CONFIGURATION GUIDE

NA, EMEA, APAC: ENGLISH

CR2300  
CR2600 (XHD)  
CR3600 (DPM)



CONFIGURATION GUIDE: VERSION 13

SUPPORTED FIRMWARE: READERS 0956+, MODEM 2000+

RELEASE DATE: NOVEMBER 2014



[www.codecorp.com](http://www.codecorp.com)



User Manuals



[YouTube.com/codecorporation](https://YouTube.com/codecorporation)

**code**  
ADVANCED BARCODE READERS

# Table of Contents

<b>Bluetooth Settings .....</b>	<b>7</b>
Bluetooth Radio Disconnect (Reconnect via QuickConnect Code) .....	7 (A2)
Bluetooth Auto Reconnect On - Default.....	7 (A3)
Bluetooth Auto Reconnect Off.....	7 (A4)
Bluetooth Radio Out of Range Beep On (CR2300 Default).....	7 (B1)
Bluetooth Radio Out of Range Beep and Vibrate Off - Default (CR2600, CR3600).....	7 (B2)
Bluetooth Radio Out of Range Beep and Vibrate On (CR2600, CR3600).....	7 (B3)
Bluetooth Radio Out of Range Vibrate On (CR2600, CR3600) .....	7 (B4)
<b>Batch Mode Settings.....</b>	<b>7-8</b>
Batch Mode Disable - Default .....	7 (C2)
Batch Mode Enable - Log Only.....	7 (C3)
Batch Mode Enable - Send and Log.....	7 (C4)
Batch Mode Auto Transfer Buffer Memory On .....	7 (D1)
Batch Mode Auto Transfer Buffer Memory Off .....	7 (D2)
Batch Mode Transfer All Data and Images in Memory .....	7 (D3)
Batch Mode Transfer Only Unsent Data in Memory.....	7 (D4)
Delete Buffered Scan Data .....	7 (E1)
USB Keyboard Mode - Batch Mode Only .....	7 (E2)
USB Virtual COM - 1 Way Mode - Batch Mode Only .....	7 (E3)
USB Speed - High Speed - Default Batch Mode Only .....	7 (E4)
USB Speed - Full Speed - Batch Mode Only.....	8 (A1)
<b>General Modem Settings .....</b>	<b>8</b>
Preemptive Mode On.....	8 (A3)
Preemptive Mode Off - Default.....	8 (A4)
Reader Paging On - Default .....	8 (B1)
Reader Paging Off .....	8 (B2)
<b>General Reading Mode Settings .....</b>	<b>8</b>
Continuous Scan Both Imagers On .....	8 (B4)
Continuous Scan Off - Default.....	8 (C1)
Cart Charger Motion Detection On .....	8 (C2)
Cart Charger Motion Detection Off - Default .....	8 (C3)
Anti-Glare On (CR2600, CR3600).....	8 (C4)
Anti-Glare Off - Default (CR2600, CR3600) .....	8 (D1)
Mirroring On.....	8 (D2)
Mirroring Off - Default.....	8 (D3)
Targeting On - Default .....	8 (D4)
Targeting Off .....	8 (E1)
Cell Phone Reading Enhancement On .....	8 (E2)
Cell Phone Reading Enhancement Off - Default .....	8 (E3)
<b>Data Formatting (Prefix/Suffix) Settings.....</b>	<b>9-10</b>
Erase Prefix & Suffix Data - Default .....	9 (A2)
Erase Prefix Data - Default.....	9 (A3)
Erase Suffix Data - Default .....	9 (A4)
Prefix AIM ID On .....	9 (B1)
Prefix AIM ID Off - Default.....	9 (B2)
Prefix Carriage Return Line Feed (RS232 Mode Only).....	9 (B3)
Prefix Comma.....	9 (B4)
Prefix Space.....	9 (C1)
Prefix Tab (USB Keyboard Mode Only) .....	9 (C2)
Prefix Tab (RS232 Mode Only) .....	9 (C3)
Suffix Carriage Return (RS232 Mode Only) .....	9 (C4)
Suffix Carriage Return Line Feed (RS232 Mode Only) .....	9 (D1)
Suffix Comma.....	9 (D2)
Suffix Enter (USB Keyboard Mode Only) .....	9 (D3)
Suffix Line Feed (RS232 Mode Only).....	9 (D4)



## Table of Contents

Suffix Space.....	9 (E1)
Suffix Tab (USB Keyboard Mode Only) .....	9 (E2)
Suffix Tab (RS232 Mode Only).....	9 (E3)
Translate all Characters to Uppercase On .....	9 (E4)
Translate all Characters to Uppercase Off - Default .....	10 (A1)
<b>Symbolologies.....</b>	<b>10-15</b>
Australian Post On .....	10 (A3)
Australian Post Off - Default .....	10 (A4)
Aztec On - Default .....	10 (B1)
Aztec Off .....	10 (B2)
Aztec Inverse On.....	10 (B3)
Aztec Inverse & Normal On .....	10 (B4)
Codabar On - Default.....	10 (C1)
Codabar Off.....	10 (C2)
Codablock F On .....	10 (C3)
Codablock F Off - Default .....	10 (C4)
Code 11 On.....	10 (D1)
Code 11 Off - Default.....	10 (D2)
Code 11 Checksum Stripped from Result On .....	10 (D3)
Code 128 On - Default .....	10 (D4)
Code 128 Off .....	10 (E1)
Code 32 (Italian Pharmacode) On.....	10 (E2)
Code 32 (Italian Pharmacode) Off - Default.....	10 (E3)
Code 39 On - Default .....	11 (A1)
Code 39 Off .....	11 (A2)
Code 39 Checksum On .....	11 (A3)
Code 39 Checksum Off - Default .....	11 (A4)
Code 39 Checksum Stripped from Result On .....	11 (B1)
Code 39 Extended Full ASCII On.....	11 (B2)
Code 39 Extended Full ASCII Off - Default.....	11 (B3)
Code 93 On - Default .....	11 (C1)
Code 93 Off .....	11 (C2)
Composite On.....	11 (C3)
Composite Off - Default.....	11 (C4)
Data Matrix Inverse On - Default.....	11 (D1)
Data Matrix Inverse Off.....	11 (D2)
Data Matrix Standard and Rectangle (Defaulted On and Cannot be Disabled)	
All GS1 DataBar On - Default.....	11 (D3)
All GS1 DataBar Off .....	11 (D4)
GS1 DataBar Omnidirectional and GS1 DataBar Truncated On .....	11 (E1)
GS1 DataBar Omnidirectional and GS1 DataBar Truncated Off.....	11 (E2)
GS1 DataBar Expanded On .....	11 (E3)
GS1 DataBar Expanded Off .....	11 (E4)
GS1 DataBar Expanded Stacked On .....	12 (A1)
GS1 DataBar Expanded Stacked Off .....	12 (A2)
GS1 DataBar Limited On .....	12 (A3)
GS1 DataBar Limited Off.....	12 (A4)
GS1 DataBar Stacked and GS1 DataBar Omnidirectional On.....	12 (B1)
GS1 DataBar Stacked and GS1 DataBar Omnidirectional Off .....	12 (B2)
Han Xin On .....	12 (B3)
Han Xin Off - Default .....	12 (B4)
Hong Kong 2 of 5 On .....	12 (C1)
Hong Kong 2 of 5 Off - Default .....	12 (C2)
IATA 2 of 5 On (IATA 2 of 5 is a Variant of Straight 2 of 5; to Enable IATA 2 of 5 Scan Straight 2 of 5 On)	
IATA 2 of 5 Off (IATA 2 of 5 is a Variant of Straight 2 of 5; to Disable IATA 2 of 5 Scan Straight 2 of 5 Off)	
Int 2 of 5 On - Default .....	12 (C3)
Int 2 of 5 Off.....	12 (C4)
Int 2 of 5 Checksum On .....	12 (D1)
Int 2 of 5 Checksum Off - Default .....	12 (D2)
Int 2 of 5 Checksum Stripped from Result On.....	12 (D3)



## Table of Contents

Japan Post On .....	12 (D4)
Japan Post Off - Default .....	12 (E1)
KIX (Dutch Post) Code On.....	12 (E2)
KIX (Dutch Post) Code Off - Default.....	12 (E3)
Korean Post On .....	13 (A1)
Korean Post Off - Default .....	13 (A2)
Maxicode On .....	13 (A3)
Maxicode Off - Default .....	13 (A4)
Matrix 2 of 5 On .....	13 (B1)
Matrix 2 of 5 Off - Default .....	13 (B2)
Micro PDF417 On .....	13 (B3)
Micro PDF417 Off - Default.....	13 (B4)
MSI Plessey On .....	13 (C1)
MSI Plessey Off -Default .....	13 (C2)
NEC 2 of 5 On .....	13 (C3)
NEC 2 of 5 Off - Default.....	13 (C4)
PDF417 On - Default.....	13 (D1)
PDF417 Off .....	13 (D2)
Pharmacode On .....	13 (D3)
Pharmacode Off - Default .....	13 (D4)
Pharmacode Normal Barcode Decoding (Left to Right) .....	13 (E1)
Pharmacode Reverse Barcode Decoding (Right to Left).....	13 (E2)
All QR Code On .....	14 (A1)
All QR Code Off.....	14 (A2)
Standard QR Code On - Default..	14 (A3)
Standard QR Code Off.....	14 (A4)
Straight 2 of 5 On.....	14 (B1)
Straight 2 of 5 Off - Default.....	14 (B2)
Telepen On.....	14 (B3)
Telepen Off - Default.....	14 (B4)
Trioptic On .....	14 (C1)
Trioptic Off - Default .....	14 (C2)
UK Plessey On .....	14 (C3)
UK Plessey Off - Default.....	14 (C4)
UK Royal Mail On .....	14 (D1)
UK Royal Mail Off - Default .....	14 (D2)
UPC On - Default.....	14 (D3)
UPC Off.....	14 (D4)
UPC E Expansion On.....	14 (E1)
UPC E Expansion Off - Default.....	14 (E2)
UPC Supplemental On .....	14 (E3)
UPC Supplemental Off - Default .....	14 (E4)
UPU ID-Tag On.....	15 (A1)
UPU ID-Tag Off - Default .....	15 (A2)
USPS Intelligent Mail/IMB/4-State CB On .....	15 (A3)
USPS Intelligent Mail/IMB/4-State CB Off - Default .....	15 (A4)
USPS Planet On .....	15 (B1)
USPS Planet Off - Default .....	15 (B2)
USPS Postnet On .....	15 (B3)
USPS Postnet Off - Default.....	15 (B4)
<b>Direct Part Mark Reading Mode Settings (CR3600 DPM).....</b>	<b>15</b>
DPM (All) Off .....	15 (C2)
DPM (Dot Peen and Laser-Etched) On.....	15 (C3)
DPM (Dot Peen Only) On .....	15 (C4)
DPM (Laser-Etched Only) On .....	15 (D1)
<b>Keyboard Language Settings.....</b>	<b>15</b>
US English Keyboard Mapping - No Leading 0.....	15 (D3)
US English Keyboard Mapping - with Leading 0 for Non Printable ASCII.....	15 (D4)



# Table of Contents

Keyboard Control Characters for Non Printable ASCII .....	15 (E1)
Belgium Keyboard .....	15 (E2)
French Keyboard .....	15 (E3)
German Keyboard .....	15 (E4)
Japanese Keyboard .....	16 (A1)
Spanish (Latin America) Keyboard.....	16 (A2)
Swiss Keyboard .....	16 (A3)
Universal Keyboard Mapping.....	16 (A4)
<b>Operating System Settings.....</b>	<b>16</b>
Alternative Operating System (Linux/Mac) On .....	16 (B2)
Alternative Operating System (Linux/Mac) Off - Default .....	16 (B3)
<b>USB Settings (Non-Batch Mode) .....</b>	<b>16</b>
USB Keyboard Mode - Default .....	16 (C2)
USB Downloader Mode.....	16 (C3)
USB HID POS Mode .....	16 (C4)
USB Virtual COM Mode.....	16 (D1)
<b>RS232 Settings (CodeXML M3 Modem Only) .....</b>	<b>16</b>
RS232 Communication Mode .....	16 (D3)
RS232 Interface - 9600 Baud Rate .....	16 (D4)
RS232 Interface - 19200 Baud Rate .....	16 (E1)
RS232 Interface - 38400 Baud Rate .....	16 (E2)
RS232 Interface - 57600 Baud Rate .....	16 (E3)
RS232 Interface - 115200 Baud Rate - Default.....	16 (E4)
<b>Reader Feedback Settings .....</b>	<b>16-17</b>
Beep On Vibrate On - Default (CR2600, CR3600) .....	16 (A2)
Beep Off Vibrate Off (CR2600, CR3600).....	16 (A3)
Beep Off Vibrate On (CR2600, CR3600) .....	16 (A4)
Beep On Vibrate Off (CR2600, CR3600) .....	17 (B1)
Beep Volume 100% - Default .....	17 (B2)
Beep Volume 67%.....	17 (B3)
Beep Volume 33%.....	17 (B4)
Beep Volume 0%.....	17 (C1)
<b>Scan Delay.....</b>	<b>17</b>
Duplicate Scan Disabled - Default .....	17 (C3)
1 Second Duplicate Scan Delay .....	17 (C4)
2 Second Duplicate Scan Delay .....	17 (D1)
3 Second Duplicate Scan Delay .....	17 (D2)
5 Second Duplicate Scan Delay .....	17 (D3)
10 Second Duplicate Scan Delay .....	17 (D4)
30 Second Duplicate Scan Delay .....	17 (E1)
1 Hour Duplicate Scan Delay .....	17 (E2)
1 Day Duplicate Scan Delay.....	17 (E3)
<b>Power Settings .....</b>	<b>18</b>
Power Off in 1 Hour .....	18 (A2)
Power Off in 2 Hours .....	18 (A3)
Power Off in 4 Hours .....	18 (A4)
<b>Miscellaneous Settings.....</b>	<b>18</b>
Read Both Wide and High Density Field - Default .....	18 (B2)
Read High Density Field Only .....	18 (B3)
Read Wide Field Only.....	18 (B4)
Handle Trigger Take Picture .....	18 (C1)
Main Left (CR3600) / Bottom (CR2300/CR2600) Button Take Picture .....	18 (C2)
Main Right (CR3600) / Top (CR2300/CR2600) Button Take Picture.....	18 (C3)





## Table of Contents

<b>Reader/Modem Commands .....</b>	<b>18</b>
Reader ID and Firmware Version.....	18 (D2)
Modem ID and Firmware Version .....	18 (D3)
Reader Text Commands On .....	18 (D4)
Reader Text Commands Off - Default .....	18 (E1)
<b>Reset, Clear, and Save Reader Settings.....</b>	<b>18-19</b>
Reset Reader to RF Factory Defaults.....	18 (E3)
Clear All JavaScript Rules.....	18 (E4)
Clear All Stored Data and Images .....	19 (A1)
Save All Reader Settings .....	19 (A2)
Reboot Reader.....	19 (A3)



# CR2300/CR2600/CR3600 Configuration Guide

*NOTE: The configuration change will take effect immediately and be saved to memory.*

Bluetooth Settings	Bluetooth Radio Disconnect (Reconnect via QuickConnect Code)	Bluetooth Auto Reconnect On - Default	Bluetooth Auto Reconnect Off
	 M10177_01	 M10365_01	 M10364_01
	A2	A3	A4
Bluetooth Radio Out of Range Beep On (CR2300 Default)	Bluetooth Radio Out of Range Beep and Vibrate Off - Default (CR2600 & CR3600)	Bluetooth Radio Out of Range Beep and Vibrate On (CR2600 & CR3600)	Bluetooth Radio Out of Range Vibrate On (CR2600 & CR3600)
 M10173_01	 M10176_01	 M10175_01	 M10174_01
	B1	B2	B3
			B4
Batch Mode Settings	Batch Mode Disable - Default	Batch Mode Enable - Log Only	Batch Mode Enable - Send and Log
	 M10187_04	 M10188_04	 M10186_04
	C2	C3	C4
Batch Mode Auto Transfer Buffer Memory On	Batch Mode Auto Transfer Buffer Memory Off	Batch Mode Transfer All Data and Images in Memory	Batch Mode Transfer Only Unsent Data in Memory
 M10307_01	 M10308_01	 M10297_01	 M10305_01
	D1	D2	D3
			D4
Delete Buffered Scan Data	USB Keyboard Mode - Batch Mode Only	USB Virtual COM - 1 Way Mode - Batch Mode Only	USB Speed - High Speed - Batch Mode Only - Default
 M10306_01	 M10200_01	 M10005_01	 M10160_01
	E1	E2	E3
			E4



# CR2300/CR2600/CR3600 Configuration Guide

*NOTE: The configuration change will take effect immediately and be saved to memory.*

USB Speed - Full Speed - Batch Mode Only	General Modem Settings	Preemptive Mode On	Preemptive Mode Off - Default
 M10161_01	<b>General Modem Settings</b>	 M10225_01	 M10226_01
A1		A3	A4
Reader Paging On - Default	Reader Paging Off	General Reading Mode Settings	Continuous Scan Both Imagers On
 M10155_01	 M10156_01		 M10012_02
B1	B2		B4
Continuous Scan Off - Default	Cart Charger Motion Detection - On	Cart Charger Motion Detection - Off	Anti-Glare On (CR2600, CR3600)
 M10011_01	 M10373_01	 M10374_02	 M10352_01
C1	C2	C3	C4
Anti-Glare Off - Default (CR2600, CR3600)	Mirroring On	Mirroring Off - Default	Targeting On - Default
 M10433_01	 M10125_01	 M10124_02	 M10153_01
D1	D2	D3	D4
Targeting Off	Cell Phone Reading Enhancement On	Cell Phone Reading Enhancement Off - Default	Intentionally Blank
 M10154_01	 M10163_01	 M10162_01	
E1	E2	E3	E4



# CR2300/CR2600/CR3600 Configuration Guide

*NOTE: The configuration change will take effect immediately and be saved to memory.*

		Erase Prefix & Suffix Data - Default	Erase Prefix Data - Default	Erase Suffix Data - Default
<b>Data Formatting (Prefix / Suffix) Settings</b>		 M10135_01	 M10126_01	 M10130_01
		A2	A3	A4
Prefix AIM ID On	Prefix AIM ID Off - Default	Prefix Carriage Return Line Feed (RS232 Mode Only)	Prefix Comma	
 M10199_01	 M10198_01	 M10405_01	 M10127_01	
B1	B2	B3	B4	
Prefix Space	Prefix Tab (USB Keyboard Mode Only)	Prefix Tab (RS232 Mode Only)	Suffix Carriage Return (RS232 Mode Only)	
 M10128_01	 M10129_01	 M10319_01	 M10320_01	
C1	C2	C3	C4	
Suffix Carriage Return Line Feed (RS232 Mode Only)	Suffix Comma	Suffix Enter (USB Keyboard Mode Only)	Suffix Line Feed (RS232 Mode Only)	
 M10322_01	 M10131_01	 M10134_01	 M10321_01	
D1	D2	D3	D4	
Suffix Space	Suffix Tab (USB Keyboard Mode Only)	Suffix Tab (RS232 Mode Only)	Translate all Characters to Uppercase On	
 M10132_01	 M10133_01	 M10323_01	 M10220_03	
E1	E2	E3	E4	



# CR2300/CR2600/CR3600 Configuration Guide

*NOTE: The configuration change will take effect immediately and be saved to memory.*

<p>Translate all Characters to Uppercase Off - Default</p>  <p>M10426_02</p>	<p>Symbologies</p>	<p>Australian Post On</p>  <p>M10288_02</p>	<p>Australian Post Off - Default</p>  <p>M10289_02</p>
<p>Aztec On - Default</p>  <p>M10018_01</p>	<p>Aztec Off</p>  <p>M10019_01</p>	<p>Aztec Inverse On</p>  <p>M10020_01</p>	<p>Aztec Inverse &amp; Normal On</p>  <p>M10021_01</p>
<p>Codabar On - Default</p>  <p>M10022_01</p>	<p>Codabar Off</p>  <p>M10023_01</p>	<p>Codablock F On</p>  <p>M10027_01</p>	<p>Codablock F Off - Default</p>  <p>M10026_01</p>
<p>Code 11 On</p>  <p>M10029_01</p>	<p>Code 11 Off - Default</p>  <p>M10028_01</p>	<p>Code 11 Checksum Stripped from Result On</p>  <p>M10031_01</p>	<p>Code 128 On - Default</p>  <p>M10044_01</p>
<p>Code 128 Off</p>  <p>M10045_01</p>	<p>Code 32 (Italian Pharmacode) On</p>  <p>M10239_02</p>	<p>Code 32 (Italian Pharmacode) Off - Default</p>  <p>M10238_02</p>	<p>Intentionally Blank</p>



# CR2300/CR2600/CR3600 Configuration Guide

*NOTE: The configuration change will take effect immediately and be saved to memory.*

Code 39 On - Default	Code 39 Off	Code 39 Checksum On	Code 39 Checksum Off - Default
 M10033_02	 M10034_02	 M10036_01	 M10035_01
A1	A2	A3	A4
Code 39 Checksum Stripped from Result On	Code 39 Extended Full ASCII On	Code 39 Extended Full ASCII Off - Default	Intentionally Blank
 M10037_01	 M10039_01	 M10038_01	
B1	B2	B3	B4
Code 93 On - Default	Code 93 Off	Composite On	Composite Off - Default
 M10042_01	 M10043_01	 M10047_01	 M10046_01
C1	C2	C3	C4
Data Matrix Inverse On - Default	Data Matrix Inverse Off	All GS1 DataBar On - Default	All GS1 DataBar Off
 M10051_03	 M10050_03	 M10054_01	 M10055_01
D1	D2	D3	D4
GS1 DataBar Omnidirectional and GS1 DataBar Truncated On	GS1 DataBar Omnidirectional and GS1 DataBar Truncated Off	GS1 DataBar Expanded On	GS1 DataBar Expanded Off
 M10057_03	 M10355_02	 M10059_03	 M10417_02
E1	E2	E3	E4



# CR2300/CR2600/CR3600 Configuration Guide

*NOTE: The configuration change will take effect immediately and be saved to memory.*

GS1 DataBar Expanded Stacked On	GS1 DataBar Expanded Stacked Off	GS1 DataBar Limited On	GS1 DataBar Limited Off
 M10357_02	 M10356_02	 M10056_03	 M10354_02
A1	A2	A3	A4
GS1 DataBar Stacked and GS1 DataBar Stacked Omnidirectional On	GS1 DataBar Stacked and GS1 DataBar Stacked Omnidirectional Off	Han Xin On	Han Xin Off - Default
 M10058_03	 M10353_03	 M10248_01	 M10249_01
B1	B2	B3	B4
Hong Kong 2 of 5 On	Hong Kong 2 of 5 Off - Default	Int 2 of 5 On - Default	Int 2 of 5 Off
 M10079_01	 M10078_02	 M10060_01	 M10061_01
C1	C2	C3	C4
Int 2 of 5 Checksum On	Int 2 of 5 Checksum Off - Default	Int 2 of 5 Checksum Stripped from Result On	Japan Post On
 M10235_01	 M10234_01	 M10065_01	 M10292_02
D1	D2	D3	D4
Japan Post Off - Default	KIX (Dutch Post) Code On	KIX (Dutch Post) Code Off - Default	Intentionally Blank
 M10293_02	 M10290_02	 M10291_02	
E1	E2	E3	E4



# CR2300/CR2600/CR3600 Configuration Guide

*NOTE: The configuration change will take effect immediately and be saved to memory.*

Korean Post On	Korean Post Off - Default	Maxicode On	Maxicode Off - Default
 M10358_01	 M10359_01	 M10067_02	 M10066_01
A1	A2	A3	A4
Matrix 2 of 5 On	Matrix 2 of 5 Off - Default	Micro PDF417 On	Micro PDF417 Off - Default
 M10069_01	 M10068_01	 M10073_01	 M10072_01
B1	B2	B3	B4
MSI Plessey On	MSI Plessey Off -Default	NEC 2 of 5 On	NEC 2 of 5 Off - Default
 M10076_01	 M10077_01	 M10082_01	 M10083_01
C1	C2	C3	C4
PDF417 On - Default	PDF417 Off	Pharmacode On	Pharmacode Off - Default
 M10070_01	 M10071_01	 M10275_02	 M10274_03
D1	D2	D3	D4
Pharmacode Normal Barcode Decoding (Left to Right)	Pharmacode Reverse Barcode Decoding (Right to Left)	Intentionally Blank	Intentionally Blank
 M10281_02	 M10280_02	E3	E4
E1	E2		



# CR2300/CR2600/CR3600 Configuration Guide

*NOTE: The configuration change will take effect immediately and be saved to memory.*

All QR Code On   M10101_02	All QR Code Off   M10351_03	Standard QR Code On - Default   M10095_03	Standard QR Code Off   M10096_02
A1	A2	A3	A4
Straight 2 of 5 On   M10241_01	Straight 2 of 5 Off - Default   M10240_01	Telepen On   M10103_01	Telepen Off - Default   M10104_01
B1	B2	B3	B4
Trioptic On   M10041_01	Trioptic Off - Default   M10040_01	UK Plessey On   M10237_02	UK Plessey Off - Default   M10236_02
C1	C2	C3	C4
UK Royal Mail On   M10294_02	UK Royal Mail Off - Default   M10295_02	UPC On - Default   M10105_01	UPC Off   M10106_01
D1	D2	D3	D4
UPC E Expansion On   M10108_01	UPC E Expansion Off - Default   M10107_01	UPC Supplemental On   M10110_01	UPC Supplemental Off - Default   M10109_01
E1	E2	E3	E4



# CR2300/CR2600/CR3600 Configuration Guide

*NOTE: The configuration change will take effect immediately and be saved to memory.*

UPU ID-Tag On   M10360_02	UPU ID-Tag Off - Default   M10361_02	USPS Intelligent Mail/IMB/ 4-State CB On   M10286_02	USPS Intelligent Mail/IMB/ 4-State CB Off   M10287_02
A1	A2	A3	A4
USPS Planet On   M10284_02	USPS Planet Off - Default   M10285_02	USPS Postnet On   M10282_02	USPS Postnet Off - Default   M10283_02
B1	B2	B3	B4
<b>Direct Part Mark Reading Mode Settings (CR3600 DPM)</b>	DPM (All) Off   M10369_01	DPM (Dot Peen and Laser-Etched) On   M10372_01	DPM (Dot Peen Only) On   M10370_01
C1	C2	C3	C4
DPM (Laser-Etched Only) On   M10371_01	Reader Keyboard Language Settings	US English Keyboard Mapping - No Leading 0   M10111_01	US English Keyboard Mapping - with Leading 0 for Non Printable ASCII   M10411_01
D1		D3	D4
Keyboard Control Characters for Non Printable ASCII   M10412_01	Belgium Keyboard   M10115_01	French Keyboard   M10414_01	German Keyboard   M10415_01
E1	E2	E3	E4



# CR2300/CR2600/CR3600 Configuration Guide

*NOTE: The configuration change will take effect immediately and be saved to memory.*

Japanese Keyboard	Spanish (Latin America) Keyboard	Swiss Keyboard	Universal Keyboard Mapping
 M10416_01	 M10120_02	 M10116_01	 M10413_01
A1	A2	A3	A4
<b>Operating System Settings</b>	Alternative Operating System (Linux/Mac) On   M10123_02	Alternative Operating System (Linux/Mac) Off - Default   M10122_02	Intentionally Blank
<b>USB Settings (Non-Batch Mode)</b>	USB Keyboard Mode - Default   M10189_01	USB Downloader Mode   M10004_02	USB HID POS Mode   M10007_03
	B2	B3	B4
USB Virtual COM Mode   M10427_01	RS232 Settings (CodeXML M3 Modem Only)  	RS232 Communication Mode   M10242_01	RS232 Interface - 9600 Baud Rate   M10243_01
D1		D3	D4
RS232 Interface - 19200 Baud Rate   M10244_01	RS232 Interface - 38400 Baud Rate   M10245_01	RS232 Interface - 57600 Baud Rate   M10246_01	RS232 Interface - 115200 Baud Rate - Default   M10247_01
E1	E2	E3	E4

# CR2300/CR2600/CR3600 Configuration Guide


*NOTE: The configuration change will take effect immediately and be saved to memory.*

		Beep On Vibrate On - Default (CR2600, CR3600)	Beep Off Vibrate Off (CR2600, CR3600)	Beep Off Vibrate On (CR2600, CR3600)
Reader Feedback Settings		A2	A3	A4
Beep On Vibrate Off (CR2600, CR3600)	Beep Volume 100% - Default	Beep Volume 67%	Beep Volume 33%	
 M10142_01	 M10197_01	 M10196_01	 M10195_01	
B1	B2	B3	B4	
Beep Volume 0%	Scan Delay	Duplicate Scan Disabled - Default	1 Second Duplicate Scan Delay	
 M10194_01		 M10144_01	 M10145_01	
C1		C3	C4	
2 Second Duplicate Scan Delay	3 Second Duplicate Scan Delay	5 Second Duplicate Scan Delay	10 Second Duplicate Scan Delay	
 M10146_01	 M10147_01	 M10148_01	 M10149_01	
D1	D2	D3	D4	
30 Second Duplicate Scan Delay	1 Hour Duplicate Scan Delay	1 Day Duplicate Scan Delay	Intentionally Blank	
 M10150_01	 M10151_01	 M10152_01		
E1	E2	E3	E4	



# CR2300/CR2600/CR3600 Configuration Guide

*NOTE: The configuration change will take effect immediately and be saved to memory.*

	Power Off in 1 Hour	Power Off in 2 Hour	Power Off in 4 Hours
<b>Power Settings</b>	 M10316_01  A2	 M10317_01  A3	 M10318_01  A4
<b>Miscellaneous Settings</b>	Read Both Wide and High Density Field - Default   M10190_01  B2	Read High Density Field Only   M10183_01  B3	Read Wide Field Only   M10182_01  B4
Handle Trigger Take Picture	Main Left (CR3600) / Bottom (CR2300/CR2600) Button Take Picture   M10341_01  C1	Main Right (CR3600) / Top (CR2300/CR2600) Button Take Picture   M10339_01  C2	Intentionally Blank  C3
<b>Reader/Modem Commands</b>	Reader ID and Firmware Version   M10157_01  D2	Modem ID and Firmware Version   M10158_01  D3	Reader Text Commands On   M10137_01  D4
Reader Text Commands Off	Reset, Clear, and Save Reader Settings	Reset Reader to RF Factory Defaults   M10001_03	Clear All JavaScript Rules   M10139_01  E4
E1		E3	



# CR2300/CR2600/CR3600 Configuration Guide

*NOTE: The configuration change will take effect immediately and be saved to memory.*

Clear All Stored Data and Images   M10138_02	Save All Reader Settings   M10159_0	Reboot Reader   M10296_01	Intentionally Blank
A1	A2	A3	A4
Intentionally Blank	Intentionally Blank	Intentionally Blank	Intentionally Blank
B1	B2	B3	B4
Intentionally Blank	Intentionally Blank	Intentionally Blank	Intentionally Blank
C1	C2	C3	C4
Intentionally Blank	Intentionally Blank	Intentionally Blank	Intentionally Blank
D1	D2	D3	D4
Intentionally Blank	Intentionally Blank	Intentionally Blank	Intentionally Blank
E1	E2	E3	E4

